Alignments in AthenaMT

Proposing changes wrt the current system Prototype implementation Plans for the future

Vakho Tsulaia (LBNL)



ATLAS Software TIM, Glasgow June 6, 2016



Static GeoModel tree



DEPARTMENT OF

Office of Science

- **Physical Volumes.** Basic building blocks of the tree
- Full Physical Volume
 - Computes and caches its absolute transform when this method gets called

GeoVFullPhysVol::
 getAbsoluteTransform()

- **Transform.** Cannot be altered after construction
- Alignable Transform
 - Can be altered multiple times during the job by calling

GeoAlignableTransform::setDelta
(const HepGeom::Transform3D&)



Applying alignments



- Alignment corrections are stored in the Conditions Database in the form of Delta Transforms
- Each subsystem manages its alignment data independently from other subsystem
- Alignment data is read in callbacks and is applied to GeoModel by using

GeoAlignableTransform::setDelta
(const HepGeom::Transform3D&)

• Delta is kept internally by Alignable Transform



Caching global positions





- When some client asks Full
 Physical Volume for its Global
 Position ...
- ... the Full Physical Volume computes the global position and caches it
 - This can happen at any time (not bound to any callbacks)
- Cached position is kept internally by the Full Physical Volume



Updating alignments



- When **alignments change** during the job ...
- ... callbacks overwrite previous deltas with new deltas and ...
- … Full Physical Volume position caches are cleared





Readout geometry



Alignments in MT

- The mechanism described so far **works well in serial** Athena, but it is **not going to work in MT** environment if we want to support multiple alignments in flight
- For AthenaMT we need to decouple the static (read-only) part of GeoModel from the part that is sensitive to alignment changes:
 - Deltas of Alignable Transforms
 - Position caches of Full Physical Volumes
- The proposal is to introduce a special container for the alignment-sensitive information: the Alignment Store





Alignment Store







Alignment Store (contd.)

- **The Alignment Store** is a regular **Conditions Object**, so it should be handled as any other Conditions Object in AthenaMT
 - Created by a Conditions Algorithm (replacement of current callback function)
 - Stored into Conditions Container using Write Conditions Handle
- By making **Detector Elements aware of the Alignment Store** we can hopefully **make the transition transparent to Detector Description clients**





Progress so far

- The decoupling of read-only GeoModel from the alignment-sensitive part was **tested in a prototype**, which was developed in early January
 - > The changes affected 10 out of 70+ classes in GeoModelKernel
- By that time the new Conditions Access infrastructure was not yet implemented, so the prototype did not use Conditions Handles, Conditions Containers etc.
- On the client side, the mechanism was successfully tested in TRT GeoModel
 - > The testing was done only in serial mode
 - Proof of principle ...







- Migrate the existing prototype core GeoModel and TRT_GeoModel code to the Conditions Access infrastructure in AthenaMT
- Test it in serial Athena and AthenaMT
- Discuss the implementation details with the developers of Detector Description clients
 - A presentation in RIG meeting?
- Proceed with putting the code into release, migration of all subsystems etc.



