Geant 4

Software Installation, release 7.0

http://cern.ch/geant4

Outline

- Supported platforms & compilers
- External software packages and tools
- Working area and installation area
- Toolkit installation
 - Configuring the environment manually
 - Using the *Configure* installation script
- Building an executable
- Integrating Geant4 in a software framework

Supported platforms & compilers

- UNIX systems
 - SUN-SunOS v.5.8, CC v.5.4 (WS6)
 - G4SYSTEM: SUN-CC
- Linux systems
 - Scientific Linux SLC3, g++ gcc 3.2.3
 - G4SYSTEM: Linux-g++
- Windows systems
 - Win/XP & Cygwin32, MSVC++ 7.1 .NET
 - G4SYSTEM: WIN32-VC
- Other systems, not (yet) officially supported
 - MacOS 10.3 and g++ gcc 3.3
 - G4SYSTEM: Darwin-g++









Required software

- A UNIX shell and related basic UNIX commands
- C++ compiler
 - Optional: FORTRAN compiler (f77/g77) is required for building utility tools in the *g3tog4* module
- GNU Make
 - GNU g++ is required for dependencies pre-processing
- CLHEP library (http://cern.ch/clhep)
- Geant4 toolkit

External software packages - 1

Visualization/GUI tools (optional):

- X Windows
- OpenGL or MesaGL
- VRML browser
- DAWN (PostScript renderer)
 - DAVID (Geometry debugging tool based on DAWN)
- Open Inventor or HEP Inventor
 - requires OpenGL/MesaGL
- Open Scientist
 - interactive environment, including GUI
- Momo
 - Tcl/Tk or Java-based GUI environment
 - GGE, GPE graphics editors
- WIRED
 - Uses the HepRep built-in graphics driver

External software packages - 2

Module and Tools for analysis (optional)

- AIDA (Abstract Interfaces for Data Analysis)
 - JAS (Java Analysis Studio)
 - PI (Physicist Interfaces for AIDA Interactive Analysis)
 - Open Scientist (Interactive Analysis Environment)
 - Any other analysis tool compliant with AIDA interfaces ...

Working area & Installation area

- Why two different areas?
 - To allow centralized installation of the Geant4 kernel libraries and related sources in a multi-user environment
 - To decouple user-developed code and applications from the kernel
 - To allow an easy integration of the Geant4 software in an existing software framework
 - To allow multiple installations of the kernel and user code
- Working and Installation area can be the same
- Are controlled by two environment variables
 - G4WORKDIR and G4INSTALL

Configuring the environment:

the manual approach for installation

- Identify the system used for the installation
 - G4SYSTEM
- Identify the area of installation (i.e. path where the source code and the kernel libraries should be based)
 - G4INSTALL
 - Optionally, specify a different path for the kernel libraries and/or the temporary object files
 - G4LIB, G4TMP
 - Optionally, specify a different path for exporting of source header files
 - G4INCLUDE

Configuring the environment:

the manual approach for installation

- Specify the path of installation for CLHEP
 - CLHEP_BASE_DIR
 - should point to the area where include/ and lib/ are placed from the standard CLHEP installation procedure
 - Paths can be customised: CLHEP_INCLUDE_DIR, CLHEP_LIB_DIR
 - the CLHEP library name is assumed to be: [lib]CLHEP[.a/.lib]
 - A different name can be explicitly specified: CLHEP_LIB
- Specify the graphics/UI drivers to install
 - G4VIS BUILD <name> DRIVER
 - G4UI BUILD <name> DRIVER
 - the path to the related graphics/(G)UI packages, if required

Configuring the environment:

the manual approach for installation

- Specify installation specific attributes
 - G4DEBUG
 - To build libraries including debug symbolic information
 - By default, optimised mode is selected
 - G4LIB_BUILD_SHARED
 - To specify if to build kernel libraries as shared libraries
 - Static archive libraries are built by default
 - Adding also G4LIB_BUILD_STATIC will build both
 - G4_NO_VERBOSE
 - For better performance, verbosity code can be left out by defining this flag (i.e. no verbosity will be possible). The default is with verbosity on

Starting the installation

- Choose the installation layout
 - Maximum granularity of libraries (granular libraries)
 - Ideal for developers and local installations
 - Link list of libraries automatically generated
 - Triggered with "gmake" from \$G4INSTALL/source
 - Category compound libraries (*global* libraries)
 - Convenient for a centralized multi-users installation
 - Default for shared libraries builds
 - Triggered with "gmake global" from \$G4INSTALL/source
- Installing source header files
 - G4 INCLUDE defines the installation path
 - Triggered by "gmake includes" from \$G4INSTALL/source
- Installing the hadronic physics-lists
 - Triggered by "gmake" from \$G4INSTALL/hadronic_lists/lists

Configuring the environment to use Geant4

- Specify the working area: G4WORKDIR
 - If not, Geant4 assumes G4 INSTALL as the working area
 - Products of application builds are placed in \$G4WORKDIR
 - Binaries in \$G4WORKDIR/bin
 - Object files and other temporary files in \$G4WORKDIR/tmp
- Specify which graphics drivers, (G)UI drivers you want to use from the current installation
 - G4VIS_USE_<name>
 - G4UI_USE_<name>
- Specify the path where to retrieve data-files for specific simulations

Using the Configure script for installation & configuration

- The **Configure** script guides through the whole installation process described so far by defining the proper environment and triggering the actual build of the libraries:
 - ./Configure -build
- Once the environment has been configured and libraries built, **Configure** stores the current installation setup, and can then be used to install the libraries in the specified "installation area":
 - ./Configure -install
 - The installation setup will become the default for the current installation, in case future changes to the installation are necessary
 - **Configure** does NOT install the hadronic physics-lists. These need to be installed manually!
- Once the installation is complete, **Configure** can be used to generate shell scripts for configuring the user environment to build a Geant4 application according to the current installation:
 - ./Configure
 - Generates env[.sh/.csh] scripts in the user's current directory
 - It assumes the user specifies a working directory (G4WORKDIR)
 - In case not, the user's home directory is set as default G4WORKDIR path

Building an executable

- Configure the environment according to the current installation
 - Source or integrate the shell script generated by Configure
- Define the working area (G4WORKDIR)
- Build any of the available examples:

```
cp -r $G4INSTALL/examples $G4WORKDIR
cd $G4WORKDIR/examples/novice/N01
gmake
```

Building DLLs on Windows

- DLLs (Dynamic Link Libraries) on Windows can be built for global compound libraries only
 - Using the Configure script
 - Follow the steps till explicitly asked for
 - Or manually with "make dll" from \$G4INSTALL/source
- Build any of the available examples by setting G4LIB USE DLL first in your environment
- Add to PATH the path where libraries are installed and run your application, e.g.:

```
export PATH=$PATH:/usr/local/geant4/lib/$G4SYSTEM
```

Integrating Geant4 in a framework

- Consider Geant4 as an external software package
- Well define its area of installation
 - For global libraries and source header files
- Choose an installation setup which best matches the project needs
- Adopt or integrate a configuration script reflecting the current installation