#### Instrumentation

#### Content

Introduction

Part 1: Passage of particles through matter

- Charges particles, Photons, Neutrons, Neutrinos
- Momentum measurements, Combining measurements.

#### Part 2: Particle Detection

- Ionisation detector
- Scintillation detectors
- Semiconductor detectors

#### **Experimental Particle Physics**

Accelerators

Luminosity, energy, quantum numbers

Detectors

• Efficiency, speed, granularity, resolution


Trigger/DAQ

- Efficiency, compression, through-put, physics models
- Offline analysis
  - Signal and background, physics models.

The primary factors for a successful experiment are the accelerator and detector/trigger system, and losses there are not recoverable.

Concentrate on electromagnetic forces since a combination of their strength and reach make them the primary responsible for energy loss in matter.

For neutrons, hadrons generally and neutrinos other effects obviously enter.



#### **PROPERTIES OF TH**

Interaction Property		Gravitational	Weak	Electromagnetic	Strong	
			(Electroweak)		Fundamental	Residual
Acts on:		Mass – Energy	Flavor	Electric Charge	Color Charge	See Residual Strong Interaction Note
Particles experiencing:		All	Quarks, Leptons	Electrically charged	Quarks, Gluons	Hadrons
Particles mediating:		Graviton (not yet observed)	W+ W- Z <sup>0</sup>	γ	Gluons	Mesons
Strength relative to electromag for two u quarks at:	10 <sup>−18</sup> m	10 <sup>-41</sup>	0.8	1	25	Not applicable
	3×10 <sup>−17</sup> m	10 <sup>-41</sup>	10 <sup>-4</sup>	1	60	to quarks
ہ for <b>two protons in nucleus</b>		10 <sup>-36</sup>	10 <sup>-7</sup>	1	Not applicable to hadrons	20

## Particle into the detectors

- From the many particles in the Particle Data Book there are only around 30 or so with life-times (cτ) > ~1µm, i.e capable of leaving a track in the detector.
- Many of these again have ct < 500µm (mm at GeV energies), and can only be seen as secondary vertices (b and c-quark systems, tau ...)
- However our detectors must be able to identify and measure momentum and energy – if possible - of:

$$e^{\pm}, \mathcal{M}^{\pm}, \mathcal{G}, \mathcal{P}^{\pm}, K^{\pm}, K^{0}, p, n, U$$

All with very specific signatures in the detector system

## Heavy charged particles


Heavy charged particles transfer energy mostly to the atomic electrons, ionising them. We will later come back to not so heavy particles, in particular electrons/positrons.

Usually the Bethe Bloch formally is used to describe this - and most of features of the Bethe Bloch formula can be understood from a very simple model :


1) Let us look at energy transfer to a single electron from heavy charged particle passing at a distance b

2) Let us multiply with the number of electrons passed

3) Let us integrate over all reasonable distances b




### Heavy charges particles



Steinar Stapnes

## **Electrons and Positrons**




## Photons

#### Three processes :

Photoelectric effect (Z<sup>5</sup>); absorption of a photon by an atom ejecting an electron. The cross-section shows the typical shell structures in an atom.


Compton scattering (Z); scattering of a photon again a free electron (Klein Nishina formula). This process has well defined kinematic constraints (giving the so called Compton Edge for the energy transfer to the electron etc) and for energies above a few MeV 90% of the energy is transferred (in most cases).

Pair-production (Z<sup>2</sup>+Z); essentially bremsstrahlung again with the same machinery as used earlier; threshold at 2 m<sub>e</sub> = 1.022 MeV. Dominates at a high energy.



Plots from C.Joram


## Electromagnetic calorimeters



Electron shower in a cloud chamber with lead absorbers

From C.Joram

Considering only Bremsstrahlung and Pair Production with one splitting per radiation length (either Brems or Pair) we can extract a good model for EM showers.



Text from C.Joram

• Additional strong interactions for hadrons (p,n, etc) ; hadronic absorption/inter action length and hadronic showers Neutrinos interact only weakly  $\rightarrow$  tiny cross-sections For their detection we need again first a charged particle.

Possible detection reactions:

- $\quad \bullet \quad \nu_\ell + n \rightarrow \ell^- + p \qquad \ell = e, \ \mu, \tau$
- $\overline{v_{\ell}}$  + p  $\rightarrow \ell^{+}$  + n  $\ell$  = e,  $\mu, \tau$

The cross-section for the reaction  $v_e + n \rightarrow e^- + p$  is of the order of 10<sup>-43</sup> cm<sup>2</sup> (per nucleon,  $E_n \approx$  few MeV).  $\rightarrow$  detection efficiency  $\varepsilon_{det} = \sigma \cdot N^{surf} = \sigma \cdot \rho \frac{N_A}{A} d$ 

1 m lron:  $\varepsilon_{det} \approx 5 \cdot 10^{-17}$ 

Neutrino detection requires big and massive detectors (ktons) and high neutrino fluxes.

In collider experiments fully hermetic detectors allow to detect neutrinos indirectly:

- Sum up all visible energy and momentum.
- Attribute missing energy and momentum to neutrino.

#### Neutrinos

## Arrangement of detectors

 $\mu^+$ 

n

combination of information can provide particle identification; for example p versus EM energy for electrons; EM/HAD provide additional information, so does muon detectors, EM response without tracks indicate a photon; secondary vertices identify b,c,  $\tau$ 's; isolation cuts help to identify leptons

We see that various

detectors and

From C.Joram


Low dereited contraction of the traction of th vertex location (Si detectors) 🐬 main tracking (gas or Si detectors) 🔊 particle identification **7** e.m. calorimetry 🐬 magnet coil 🐬

hadron calorimetry / return yoke **7** muon identification / tracking **7** 




## **Magnetic fields**

#### Magnetic field configurations:



See the Particle Data Book for a discussion of magnets, stored energy, fields and costs.

#### Momentum measurement



the sagitta s is determined by 3 measurements with error  $\sigma(x)$ :  $s = x_2 - \frac{x_1 + x_3}{2}$  $\frac{\sigma(p_T)}{p_T}\Big|_{p_T}^{meas.} = \frac{\sigma(s)}{s} = \frac{\sqrt{\frac{3}{2}}\sigma(x)}{s} = \frac{\sqrt{\frac{3}{2}}\sigma(x) \cdot 8p_T}{0.3 \cdot BL^2}$ 

for N equidistant measurements, one obtains (R.L. Gluckstern, NIM 24 (1963) 381)

$$\frac{\sigma(p_T)}{p_T} \bigg|_{p_T}^{meas.} = \frac{\sigma(x) \cdot p_T}{0.3 \cdot BL^2} \sqrt{720/(N+4)} \quad \text{(for N } \ge \approx 10\text{)}$$

ex:  $p_T$ =1 GeV/c, L=1m, B=1T,  $\sigma(x)$ =200 $\mu$ m, N=10

$$\frac{\sigma(p_T)}{p_T}\Big|^{meas.} \approx 0.5\% \qquad (s \approx 3.75 \text{ cm})$$

## Magnetic fields

How are reactions of the various particles with detectors turned into electrical signals. We would like to extract position and energy information channel by channel from our detectors.

Three effects are usually used :

- 1 Ionisation
- **2** Scintillation
- 3 Semi Conductors

and these are used in either for tracking, energy measurements, photon detectors for Cherenkov or TRT, etc

and from then on it is all online (trigger, DAQ) and offline treatment and analysis ....

#### **Ionisation Detectors**


The different regions :

Recombination before collection.

lonisation chamber; collect all primary charge. Flat area.


Proportional counter (gain to 10<sup>6</sup>); secondary avalanches need to be quenched. Limited proportionality (secondary avalanches distorts field, more quenching needed).

Geiger Muller mode, avalanches all over wire, strong photoemission, breakdown avoided by cutting HV.



Advanced calculations of electric field, drift, diffusion and signal formation can be done with Garfield.

## **Ionisation Detectors**




x (čm)

Two dimensional readout can be obtained by; crossed wires, charge division with resistive wires, measurement of timing differences or segmented cathode planes with analogue readout

**Resolution given by (binary readout):**  $\sigma = d / \sqrt{12}$ 

Analogue readout and charge sharing can improve this significantly when the left/right signal size provide more information about the hit position.




 $y = \frac{\sum (Q_i - b) y_i}{\sum (Q_i - b)} ,$ 

Steinar Jupnes

## **Scintillators**


Inorganic Crystalline Scintillators The most common inorganic scintillator is sodium iodide activated with a trace amount of thallium [NaI(TI)],


#### Energy bands in impurity activated crystal




Valence Band


Strong dependence of the light output and the decay time with temperature.








## Scintillators



#### **Semi-Conductors**





Intrinsic silicon will have electron density = hole density; 1.45  $10^{10}$  cm<sup>-3</sup> (from basic semiconductor theory).

In the volume above this would correspond to 4.510<sup>8</sup> free charge carriers; compared to around  $3.2 \ 10^4$ produces by MIP (Bethe Bloch loss in 300um Si divided by 3.6 eV).

Need to decrease number of free carriers; use depletion zone (reduce temperature would also help but one would need to go to cryogenic temperatures)


### **Semi-Conductors**






## **Semi-Conductors**


#### **The DELPHI Vertex Detector**



K0 and Lambda reconstruction




From CERN-CLAF, O.Ullaland




## Front End electronics


Most detectors rely critically on low noise electronics. A typical Front End is shown below :




where the detector is represented by the capasitance  $C_d$ , bias voltage is applied through  $R_b$ , and the signal is coupled to the amplifier though a capasitance  $C_c$ . The resistance  $R_s$  represent all the resistances in the input path. The preamplifier provides gain and feed a shaper which takes care of the frequency response and limits the duration of the signal.

The equivalent circuit for noise analysis includes both current and voltage noise sources labelled i<sub>n</sub> and e<sub>n</sub> respectively. Two important noise sources are the detector leakage current (fluctuating-some times called shot noise) and the electronic noise of the amplifier, both unavoidable and therefore important to control and reduce. The diagram below show the noise sources and their representation in the noise analysis: DETECTOR BIAS SERIES AMPLIFIER +







# LCG

# The Data Acquisition

~ 300.000 MB/s from all sub-detectors

#### Trigger and data acquisition




~ 300MB/s Raw Data


#### Event filter computer farm



#### Tier 0 at CERN: Acquisition, First pass processing Storage & Distribution



#### Palloon Sokm CD stack with 1 year LHC data - 20 Km Mt Blanc 4.8 km



Concorde

15 Km

Tier-0 (CERN): •Data recording •Initial data reconstruction •Data distribution

Tier-1 (11 centres): •Permanent storage •Re-processing •Analysis

Tier-2 (~130 centres): • Simulation

• End-user analysis



Astronomy & Astrophysics **Civil Protection Computational Chemistry Comp. Fluid Dynamics Computer Science/Tools Condensed Matter Physics Earth Sciences** Finance Fusion High Energy Physics **Humanities** Life Sciences Material Sciences Social Sciences

~285 sites 48 countries >350,000 CPU cores >80 PetaBytes disk, >80PB tape >13,000 users >12 Million jobs/month 21:13:50 UTC



### Instrumentation


We now know how most particles ( i.e all particles that live long enough to reach a detector; e,u,p, $\pi$ ,k,n, $\gamma$ , neutrinos,etc) react with matter.

We now know how to identify particles to some extend, how to measure E and p, v, and how to measure lifetimes using secondary vertices, etc

Essential three detector types are used :

- 1 Ionisation detectors
- 2 Scintillators
- **3 Semi Conductors**

4 Finally we have looked briefly at how electrical signals are treated in FE electronics



The detector-types mentioned are either for tracking, energy measurement, photon detectors, etc in various configurations.