


Review of Electromagnetism



This review is not meant to teach the subject, but to repeat and to refresh, at least partially, what you have learnt at university.

Maxwell's equations

(in material)

$$\oint \vec{H}(\vec{r}, t) \cdot d\vec{s} = \iint \vec{J}(\vec{r}, t) \cdot d\vec{A} + \frac{d}{dt} \iint \vec{D}(\vec{r}, t) \cdot d\vec{A}$$

$$\oint \vec{E}(\vec{r}, t) \cdot d\vec{s} = -\frac{d}{dt} \iint \vec{B}(\vec{r}, t) \cdot d\vec{A}$$

$$\oiint \vec{D}(\vec{r}, t) \cdot d\vec{A} = \iiint \rho(\vec{r}, t) dV$$

$$\oiint \vec{B}(\vec{r}, t) \cdot d\vec{A} = 0$$

\vec{E}, \vec{H} electric and magnetic field

\vec{D}, \vec{B} electric displacement and magnetic induction

\vec{J} electric current density

ρ electric charge density

$\iint \vec{J}(\vec{r}, t) \cdot d\vec{A}$ stands for all currents going through the area A. It may consist of 3 parts

$$\vec{J}(\vec{r}, t) = \vec{J}_c(\vec{r}, t) + \vec{J}_{cv}(\vec{r}, t) + \vec{J}_i(\vec{r}, t)$$

$\vec{J}_c(\vec{r}, t) = \kappa \vec{E}(\vec{r}, t)$ conduction current (Ohm's law)

$\vec{J}_{cv}(\vec{r}, t) = \rho(\vec{r}, t) \vec{v}(\vec{r}, t)$ convection current

$\vec{J}_i(\vec{r}, t)$ impressed current

$\iiint \rho(\vec{r}, t) dV$ stands for all charges in the volume V

*Current and charge may have different distributions:
point, line, surface, volume*

Maxwell's equations

(in differential form)

With Stokes' theorem:

$$\oint \vec{E} \cdot d\vec{s} = \iint (\vec{\nabla} \times \vec{E}) \cdot d\vec{A} = -\frac{d}{dt} \iint \vec{B} \cdot d\vec{A} = -\iint \frac{\partial \vec{B}}{\partial t} \cdot d\vec{A}$$

$$\iint \left[\vec{\nabla} \times \vec{E} + \frac{\partial \vec{B}}{\partial t} \right] \cdot d\vec{A} = 0$$

since this is valid for any area: $\vec{\nabla} \times \vec{E} = -\frac{\partial \vec{B}}{\partial t}$ (2)

correspondingly: $\vec{\nabla} \times \vec{H} = \vec{J} + \frac{\partial \vec{D}}{\partial t}$ (1)

With Gauss' theorem:

$$\oiint \vec{D} \cdot d\vec{A} = \iiint \vec{\nabla} \cdot \vec{D} dV = \iiint \rho dV$$

$$\iiint [\vec{\nabla} \cdot \vec{D} - \rho] dV = 0$$

since this is valid for any volume: $\vec{\nabla} \cdot \vec{D} = \rho$ (3)

correspondingly: $\vec{\nabla} \cdot \vec{B} = 0$ (4)

Time-harmonic fields

Time-harmonic fields can be written as complex quantities

$$\vec{E}(\vec{r}, t) = \vec{E}_0(\vec{r}) \cos(\omega t + \varphi) = \Re[\vec{E}_0(\vec{r}) e^{i\varphi} e^{i\omega t}] = \Re[\tilde{\vec{E}}(\vec{r}) e^{i\omega t}]$$


$\tilde{\vec{E}}(\vec{r})$ is called phasor.

- Advantages are:
- $\partial/\partial t \rightarrow i\omega$,
 - phasors are vectors in a coordinate system rotating with ωt ,
 - $e^{i\omega t}$ cancels out in the equations

We will drop the tilde on following transparencies whenever the situation is sufficiently clear!

The effect of electric fields on matter can be described by a polarization \vec{P} , the effect of magnetic fields by a magnetization \vec{M} . \vec{P} and \vec{M} result from averaging over atomic / molecular electric and magnetic dipoles, respectively.

There are several electric reactions. One is for example due to induced dipoles



$$p_e = qx \rightarrow \vec{P} = n \vec{p}_e = \epsilon_0 \chi_e \vec{E}$$

n : dipole density


χ_e : electric susceptibility

Linear materials:


$$\vec{D} = \epsilon_0 \vec{E} + \vec{P} = \epsilon_0 \vec{E} + \epsilon_0 \chi_e \vec{E} = \epsilon_r \epsilon_0 \vec{E} = \epsilon \vec{E}$$

\vec{D} : electric displacement, $\epsilon_r = 1 + \chi_e$: relative permittivity

Dielectric behavior is a dynamic process, dependent on frequency ($\epsilon_r = \epsilon_r' - i \epsilon_r''$, ϵ_r'' represents the losses):



Magnetic reaction of material is due to particle spins (magnetic moments). It can be described by means of magnetic dipoles, i.e. by circulating elementary currents:



$$p_m = \pi r_e^2 I_e \rightarrow \vec{M} = n \vec{p}_m = \chi_m \vec{H}$$

n : dipole density

χ_m : magnetic susceptibility


Linear materials:

$$\vec{B} = \mu_0 \vec{H} + \mu_0 \vec{M} = \mu_0 \vec{H} + \mu_0 \chi_m \vec{H} = \mu_r \mu_0 \vec{H} = \mu \vec{H}$$

\vec{B} : magnetic induction

$\mu_r = 1 + \chi_m$: relative permeability

For ferromagnetic materials the relation between the external field and the magnetization is non-linear and depends typically on the history of the material (hysteresis).



$$\vec{D} = \epsilon_0 \vec{E} + \epsilon_0 \chi \vec{P} \quad \text{and} \quad \vec{B} = \mu_0 \vec{H} + \mu_0 \vec{M}$$

take into account the reaction of the material on the fields averaged over all atoms and/or molecules, i.e. over all elementary electrical and magnetic dipoles.

*In many materials the relations $\vec{P} = \vec{P}(\vec{E})$ and $\vec{M} = \vec{M}(\vec{H})$ are *linear*.*

*But in general they are *nonlinear*, *anisotropic*, i.e. dependent on the direction of \vec{E} or \vec{H} , and they are *time* or *frequency dependent*.*

*They may also include *losses*.*

There are losses due to radiation and interaction between electric and magnetic dipoles

$$\epsilon = \epsilon' - i\epsilon'' = \epsilon' (1 - i \tan \delta_\epsilon)$$

$$\tan \delta_\epsilon = \epsilon'' / \epsilon', \quad \delta_\epsilon \text{ electric loss angle}$$

$$\mu = \mu' - i\mu'' = \mu' (1 - i \tan \delta_\mu)$$

$$\tan \delta_\mu = \mu'' / \mu', \quad \delta_\mu \text{ magnetic loss angle}$$

and losses due to collisions between free charges

$$\vec{\nabla} \times \vec{H} = \vec{J} + i\omega\epsilon\vec{E} = \kappa\vec{E} + i\omega\epsilon\vec{E} = i\omega\epsilon [1 + \kappa / (i\omega\epsilon)] \vec{E}$$

$$\epsilon_c = \epsilon' - i\epsilon'' = \epsilon [1 - i\kappa / (\omega\epsilon)]$$

In most dielectrics is $\tan(\delta_\epsilon) \ll 1$

In good conductors is $\kappa / \omega\epsilon \gg 1 \rightarrow \epsilon_c \approx \kappa / i\omega$

Boundary / continuity conditions

Maxwell's theory is a continuum theory. It requires continuous, double differentiable functions.


Solutions in different media have to be matched at the interface by boundary or continuity conditions.

Take Maxwell's equs. in integral form

$$\oint \vec{H}(\vec{r}, t) \cdot d\vec{s} = \iint \vec{J}(\vec{r}, t) \cdot d\vec{A} + \frac{d}{dt} \iint \vec{D}(\vec{r}, t) \cdot d\vec{A}$$

$$\oint \vec{E}(\vec{r}, t) \cdot d\vec{s} = -\frac{d}{dt} \iint \vec{B}(\vec{r}, t) \cdot d\vec{A}$$

and make an intelligent choice for the integration area:



Δs is finite but small, such that the fields are constant, then

$$\begin{aligned}
 H_{t1} \Delta s - H_n h - H_{t2} \Delta s + H_n h &= \\
 &= J_s \Delta s + \frac{\partial}{\partial t} \iint_{\Delta A} \vec{D} \cdot \Delta \vec{A}
 \end{aligned}$$

for $h \rightarrow 0$ it becomes

$$H_{t1} - H_{t2} = J_s$$

$$E_{t1} - E_{t2} = 0, \quad \text{correspondingly}$$

If medium 2 is perfectly electric conducting (pec) :

$$E_{t1} = 0, \quad H_{t1} = J_s$$


J_s is a surface current density.

An intelligent choice of the integration volume:

$$\oiint \vec{D}(\vec{r}, t) \cdot d\vec{A} = \iiint \rho(\vec{r}, t) dV$$

$$\oiint \vec{B}(\vec{r}, t) \cdot d\vec{A} = 0$$

$$D_{n1} \Delta A - D_{n2} \Delta A + \iint_{\Delta A_{\text{cyl}}} \vec{D} \cdot d\vec{A} = \rho_s \Delta A$$



for $h \rightarrow 0$ it becomes

$$D_{n1} - D_{n2} = \rho_s$$

$$B_{n1} - B_{n2} = 0, \quad \text{correspondingly}$$

If medium 2 is pec: $D_{n1} = \rho_s, \quad B_{n1} = 0$

ρ_s

ρ_s is a surface charge density.

Application of Maxwell's equations

Electrostatic fields

($H=0$, $\delta/\delta t=0$, $\epsilon=\text{const.}$)

Maxwell's equations

$$\vec{\nabla} \times \vec{E} = 0$$


$$\vec{\nabla} \cdot \vec{D} = \rho$$

$$\vec{\nabla} \times \vec{\nabla} \Phi \equiv 0: \quad \vec{\nabla} \times \vec{E} = 0 \quad \rightarrow \quad \vec{E} = -\vec{\nabla} \Phi$$

Poisson equation:

$$\vec{\nabla} \cdot \vec{D} = \vec{\nabla} \cdot (\epsilon \vec{E}) = \rho \quad \rightarrow \quad \vec{\nabla}^2 \Phi = -\frac{\rho}{\epsilon} \quad (1)$$

Example: Two round tubes forming an electrostatic lens



E-field pattern

(1) *becomes circular symmetric Laplace equation*

$$\vec{\nabla}^2 \Phi = \frac{\partial^2 \Phi}{\partial \rho^2} + \frac{1}{\rho} \frac{\partial \Phi}{\partial \rho} + \frac{\partial^2 \Phi}{\partial z^2} = 0 \quad (2)$$

Bernoulli ansatz

$$\Phi(\rho, z) = R(\rho)Z(z)$$

substituted in (2) and divided by RZ

$$\frac{1}{R} \frac{d^2 R}{d\rho^2} + \frac{1}{R\rho} \frac{dR}{d\rho} + \underbrace{\frac{1}{Z} \frac{d^2 Z}{dz^2}}_{k_z^2} = 0 \quad (3)$$

Last term is independent of ρ and must be constant. It yields

$$\frac{d^2 Z}{dz^2} - k_z^2 Z = 0$$

with solutions

$$Z = \begin{cases} C_0 + D_0 z, & k_z = 0 \\ C e^{k_z z} + D e^{-k_z z}, & k_z \neq 0 \end{cases}$$

Condition at infinity

$$\Phi \text{ finite for } z = \pm\infty: C = D_0 = 0, \quad Z = \begin{cases} C_0, & k_z = 0 \\ D e^{-k_z|z|}, & k_z \neq 0 \end{cases}$$

The left over equ.(3) is the Bessel differential equation

$$\frac{d^2 R}{d\rho^2} + \frac{1}{\rho} \frac{dR}{d\rho} + k_z^2 R = 0$$

with solutions

$$R = \begin{cases} A_0 + B_0 \ln(\rho/\rho_0), & k_z = 0 \\ A J_0(k_z \rho) + B N_0(k_z \rho), & k_z \neq 0 \end{cases}$$

Condition at $\rho \rightarrow 0$

$$\Phi \text{ finite for } \rho = 0: \quad B_0 = B = 0$$

Boundary conditions

$$\Phi = \begin{cases} -\Phi_0 & \text{for } \rho = a, z > 0 \\ +\Phi_0 & \text{for } \rho = a, z < 0 \end{cases} \quad (4)$$
$$A_0 C_0 = -\text{sign}(z) \Phi_0, \quad J_0(k_z a) = 0 \rightarrow k_{zn} a = j_{0n}$$

Using above conditions Φ becomes

$$\Phi = \text{sign}(z) \left[-\Phi_0 + \sum_{n=1}^{\infty} A_n J_0\left(j_{0n} \frac{\rho}{a}\right) e^{-j_{0n}|z|/a} \right] \quad (5)$$

and due to symmetry (4), $\Phi(z=0)=0$, (5) becomes

$$\Phi_0 = \sum_{n=1}^{\infty} A_n J_0\left(j_{0n} \frac{\rho}{a}\right) \quad (6)$$

To calculate the coefficients A_n we use a Fourier-Bessel expansion.

Multiplication of (6) with $\rho J_0(j_{0m}\rho/a)$ and integration over ρ

$$\underbrace{\Phi_0 \int_0^a J_0\left(j_{0m} \frac{\rho}{a}\right) \rho d\rho}_{\frac{a^2}{j_{0m}} J_1(j_{0m})} = \sum_{n=1}^{\infty} A_n \underbrace{\int_0^a J_0\left(j_{0n} \frac{\rho}{a}\right) J_0\left(j_{0m} \frac{\rho}{a}\right) \rho d\rho}_{\delta_m^n \frac{a^2}{2} J_1^2(j_{0m})}$$

gives the final result

$$\Phi = \text{sign}(z) \Phi_0 \left[-1 + 2 \sum_{n=1}^{\infty} \frac{J_0\left(j_{0n} \frac{\rho}{a}\right)}{j_{0n} J_1(j_{0n})} e^{-j_{0n}|z|/a} \right]$$

Stationary currents

($\delta/\delta t=0$, $\kappa=\text{const.}$)


Maxwell's equations: $\vec{\nabla} \times \vec{H} = J$, $\vec{\nabla} \times \vec{E} = 0$

$$\vec{E} = -\vec{\nabla} \Phi$$

$$\vec{\nabla} \cdot (\vec{\nabla} \times \vec{H}) = 0 = \vec{\nabla} \cdot \vec{J} = \vec{\nabla} \cdot (\kappa \vec{E}) \rightarrow \vec{\nabla}^2 \Phi = 0$$

but different boundary / continuity conditions:

here $J_n = \kappa \vec{E}_n = -\kappa d\Phi/dn = 0$.



J-field lines

Magnetostatic fields

($E=0$, $\delta/\delta t=0$, $\mu=\text{const.}$)

Maxwell's equations $\vec{\nabla} \times \vec{B} = \mu \vec{J}$, $\vec{\nabla} \cdot \vec{B} = 0$

since $\vec{\nabla} \cdot (\vec{\nabla} \times \vec{A}) \equiv 0$: $\rightarrow \vec{B} = \vec{\nabla} \times \vec{A}$

$$\vec{\nabla} \times \vec{B} = \vec{\nabla} \times (\vec{\nabla} \times \vec{A}) = \vec{\nabla} (\vec{\nabla} \cdot \vec{A}) - \vec{\nabla}^2 \vec{A} = \mu \vec{J}$$

\vec{A} is not fully determined. Substitution

$\vec{A} \rightarrow \vec{A}' + \vec{\nabla} \psi$ does not change $\vec{B} = \vec{\nabla} \times \vec{A}' = \vec{\nabla} \times \vec{A}$

Use gauge: $\vec{\nabla} \cdot \vec{A} = 0$

$$\vec{\nabla}^2 \vec{A} = -\mu \vec{J} \quad (1)$$

We decompose (1) into cartesian components

$$\vec{\nabla}^2 A_i = -\mu J_i, \quad i = x, y, z \quad (2)$$

and make use of knowledge in electro-statics to solve (2). Field and scalar potential of a point charge q (Coulomb's law) are

$$\vec{E} = \frac{q}{4\pi\epsilon r^2} \vec{e}_r = -\vec{\nabla} \Phi \rightarrow E_r = -\frac{d\Phi}{dr} \rightarrow \Phi = \frac{q}{4\pi\epsilon r}$$


Φ is solution of the Poisson equ. $\vec{\nabla}^2 \Phi = -\frac{q}{\epsilon} \delta(r)$

(2) follows from it by substituting

$$\Phi \rightarrow A_i, \quad \frac{1}{\epsilon} \rightarrow \mu, \quad q \rightarrow J_i \quad (3)$$

Next we use Φ as a „Green's function“ to calculate the potential of a charge distribution and obtain the Coulomb integral

$$\Phi(\vec{r}) = \frac{1}{4\pi\epsilon_0} \iiint \frac{\rho(\vec{r}')}{R} dV' \quad (4)$$



Substituting (3) into (4) we get the solution of (2), which becomes in vectorial form

$$\vec{A}(\vec{r}) = \frac{\mu}{4\pi} \iiint \frac{\vec{J}(\vec{r}')}{R} dV'$$

Quasi-stationary fields

$$|J| \gg \left| \frac{d\vec{D}}{dt} \right| \rightarrow \frac{\epsilon}{\kappa} = T_r \ll \frac{T}{2\pi}$$

T_r is called relaxation time

Maxwell's equations

$$\vec{\nabla} \times \vec{B} = \mu \vec{J}, \quad \vec{\nabla} \times \vec{E} = -\frac{\partial \vec{B}}{\partial t}, \quad \vec{\nabla} \cdot \vec{D} = \rho, \quad \vec{\nabla} \cdot \vec{B} = 0$$

Potentials

$$\vec{\nabla} \cdot \vec{B} = 0 \rightarrow \vec{B} = \vec{\nabla} \times \vec{A}$$

$$\vec{\nabla} \times \vec{E} = -\frac{\partial \vec{B}}{\partial t} \rightarrow \vec{\nabla} \times \left(\vec{E} + \frac{\partial \vec{A}}{\partial t} \right) = 0 \rightarrow \vec{E} = -\vec{\nabla} \Phi - \frac{\partial \vec{A}}{\partial t}$$

$$\begin{aligned}\vec{\nabla} \times \vec{B} &= \vec{\nabla} \times (\vec{\nabla} \times \vec{A}) = \vec{\nabla} (\vec{\nabla} \cdot \vec{A}) - \vec{\nabla}^2 \vec{A} = \\ &= \mu \vec{J} = \mu \kappa \vec{E} = -\vec{\nabla} (\mu \kappa \Phi) - \mu \kappa \frac{\partial \vec{A}}{\partial t}\end{aligned}$$

\vec{A} and Φ are not fully determined. Substituting

$$\vec{A} \rightarrow \vec{A}' + \vec{\nabla} \psi, \quad \Phi \rightarrow \Phi' - \frac{\partial \psi}{\partial t}$$

does not change $\vec{B} = \vec{\nabla} \times \vec{A}$, $\vec{E} = -\vec{\nabla} \Phi - \frac{\partial \vec{A}}{\partial t}$

So, use gauge: $\vec{\nabla} \cdot \vec{A} = -\mu \kappa \Phi$

$$\rightarrow \vec{\nabla}^2 \vec{A} - \mu \kappa \frac{\partial \vec{A}}{\partial t} = 0 \quad \text{diffusion equation}$$

Poynting's theorem

(ϵ , μ , $\kappa = \text{const.}$ and real, $\mathbf{J} = \kappa \mathbf{E}$,
full set of Maxwell's equations)

If fields move a charge ρdV by a distance δs in the interval δt , the work done by the fields (dissipated power) is

$$d \frac{\delta W}{\delta t} = d \vec{f} \cdot \frac{\delta \vec{s}}{\delta t} = \rho dV (\vec{E} + \vec{v} \times \vec{B}) \cdot \vec{v} = \vec{E} \cdot \rho \vec{v} dV = \vec{E} \cdot \vec{J} dV$$

Express $\vec{E} \cdot \vec{J}$ with the aid of Maxwell's equations


$$\vec{E} \cdot \vec{\nabla} \times \vec{H} = \vec{J} \cdot \vec{E} + \frac{\partial \vec{D} \cdot \vec{E}}{\partial t}$$

$$-\vec{H} \cdot \vec{\nabla} \times \vec{E} = -\frac{\partial \vec{B} \cdot \vec{H}}{\partial t}$$

$$\rightarrow -\vec{\nabla} \cdot (\vec{E} \times \vec{H}) = \vec{E} \cdot \vec{J} + \frac{\partial}{\partial t} \left[\frac{1}{2} \vec{E} \cdot \vec{D} + \frac{1}{2} \vec{H} \cdot \vec{B} \right]$$

We get Poynting's theorem after integration over V and application of Gauss' law:

$$\begin{aligned}
 & -\oint (\vec{E} \times \vec{H}) \cdot d\vec{A} = \\
 & = \iiint \vec{E} \cdot \vec{J} dV + \frac{\partial}{\partial t} \iiint \left(\frac{1}{2} \vec{E} \cdot \vec{D} + \frac{1}{2} \vec{H} \cdot \vec{B} \right) dV
 \end{aligned}$$



Poynting vector (radiation flux)	$\vec{S} = \vec{E} \times \vec{H}$
dissipated power density	$\rho_d = \vec{E} \cdot \vec{J}$
electric energy density	$w_e = (1/2) \vec{E} \cdot \vec{D}$
magnetic energy density	$w_m = (1/2) \vec{H} \cdot \vec{B}$

Energy radiated into the volume V equals the dissipation plus the increase of stored electromagnetic energy in V .

Poynting's theorem for time-harmonic fields

decompose e.g. $\vec{E} = \Re [\tilde{\vec{E}} e^{i\omega t}] = \frac{1}{2} [\tilde{\vec{E}} e^{i\omega t} + \tilde{\vec{E}}^* e^{-i\omega t}]$

$$w_e = \frac{1}{2} \vec{E} \cdot \vec{D} = \frac{1}{8} [\tilde{\vec{E}} \cdot \tilde{\vec{D}} e^{i2\omega t} + \tilde{\vec{E}}^* \cdot \tilde{\vec{D}}^* e^{-i2\omega t}] + \frac{1}{8} [\tilde{\vec{E}} \cdot \tilde{\vec{D}}^* + \tilde{\vec{E}}^* \cdot \tilde{\vec{D}}]$$
$$= \frac{1}{4} \Re [\tilde{\vec{E}} \cdot \tilde{\vec{D}} e^{i2\omega t}] + \frac{1}{4} \tilde{\vec{E}} \cdot \tilde{\vec{D}}^*$$

and after time-averaging $\bar{w}_e = (1/4) \tilde{\vec{E}} \cdot \tilde{\vec{D}}^*$

correspondingly: $\bar{w}_m = (1/4) \tilde{\vec{H}} \cdot \tilde{\vec{B}}^*$, $\bar{p}_d = (1/2) \tilde{\vec{E}} \cdot \tilde{\vec{J}}^*$

$\vec{S}_c = (1/2) \tilde{\vec{E}} \times \tilde{\vec{H}}^*$ complex, time-averaged radiation flux

Again, using Maxwell's equations

$$(1/2) \vec{\tilde{E}} \cdot \vec{\nabla} \times \vec{\tilde{H}}^* = \vec{\tilde{J}}^* - i \omega \vec{\tilde{D}}^*$$

$$\underline{-(1/2) \vec{\tilde{H}}^* \cdot \vec{\nabla} \times \vec{\tilde{E}} = -i \omega \vec{\tilde{B}}}$$

$$\rightarrow -\vec{\nabla} \cdot \left(\frac{1}{2} \vec{\tilde{E}} \times \vec{\tilde{H}}^* \right) = \frac{1}{2} \vec{\tilde{E}} \cdot \vec{\tilde{J}}^* + i 2 \omega \left(\frac{1}{4} \vec{\tilde{H}}^* \cdot \vec{\tilde{B}} - \frac{1}{4} \vec{\tilde{E}} \cdot \vec{\tilde{D}}^* \right)$$

we get Poynting's theorem after integration over V and application of Gauss' law:

$$-\oint \vec{S}_c \cdot d\vec{A} = \iiint \bar{p}_d dV + i 2 \omega \iiint (\bar{w}_m - \bar{w}_e) dV$$

Active power (time-averaged Joulean heat, dissipation)

$$\bar{P}_{act} = -\oint \Re[\vec{S}_c] \cdot d\vec{A} = \iiint \bar{p}_d dV = \bar{P}_d$$

Reactive power

$$\bar{P}_{react} = -\oint \Im[\vec{S}_c] \cdot d\vec{A} = 2 \omega \iiint (\bar{w}_m - \bar{w}_e) dV = 2 \omega (\bar{W}_m - \bar{W}_e)$$


In good conductors is $W_m \gg W_e$ ($|E| \ll |H|$)

$$-\oint \vec{S}_c \cdot d\vec{A} = \bar{P}_c = \bar{P}_d + i2\omega \bar{W}_m$$

This allows to calculate the resistance and internal inductance of a conductor. We define

$$I^* = \oint_2 \vec{H}^* \cdot d\vec{s}$$

$$U = \int_1 \vec{E} \cdot d\vec{s} = I(R + i\omega L_i)$$



and obtain

$$\bar{P}_c = \frac{1}{2} U I^* = \frac{1}{2} |I|^2 (R + i\omega L_i) = \bar{P}_d + i2\omega \bar{W}_m$$

Electromagnetic waves

$$(\epsilon, \mu = \text{const.}, \rho = J = 0)$$

The simplest electromagnetic wave is a **plane wave**. It depends only on one space variable (direction of propagation) and on the time.

$$\vec{E} = \vec{E}(z, t), \quad \vec{H} = \vec{H}(z, t)$$

First two Maxwell's eqs. $\vec{\nabla} \times \vec{H} = \epsilon \frac{\partial \vec{E}}{\partial t}$, $\vec{\nabla} \times \vec{E} = -\mu \frac{\partial \vec{H}}{\partial t}$

give two sets of uncoupled equations:

$$\begin{aligned} -\frac{\partial H_y}{\partial z} &= \epsilon \frac{\partial E_x}{\partial t} & \frac{\partial E_x}{\partial z} &= -\mu \frac{\partial H_y}{\partial t} \\ \frac{\partial H_x}{\partial z} &= \epsilon \frac{\partial E_y}{\partial t} & -\frac{\partial E_y}{\partial z} &= -\mu \frac{\partial H_x}{\partial t} \end{aligned}$$


From the red set e.g. follows the wave equation

$$\frac{\partial^2 E_x}{\partial z^2} - \frac{1}{c^2} \frac{\partial^2 E_x}{\partial t^2} = 0, \quad c = \frac{1}{\sqrt{\mu\epsilon}}$$

with d' Alembert's solution

$$E_x = f(z - ct) + g(z + ct) = E_x^+ + E_x^-$$

$$ZH_y = f(z - ct) - g(z + ct) = H_y^+ - H_y^-, \quad Z = \sqrt{\frac{\mu}{\epsilon}}$$



Similar solutions follow from the blue set with E_y and H_x .

velocity of light : $c = \frac{1}{\sqrt{\mu\epsilon}}$

wave impedance : $Z = \sqrt{\frac{\mu}{\epsilon}}$
 $\approx 377 \Omega$ in free space

field properties :

$$\vec{E} \perp \vec{H}$$

$$\vec{S} = \vec{E} \times \vec{H} \rightarrow \text{direction of propagation}$$

\vec{E}, \vec{H} are \perp to direction of propagation

$$E^+ / H^+ = -E^- / H^- = Z$$

Time-harmonic plane wave

$$\left(\frac{\partial}{\partial t} = i\omega, \epsilon_r = \epsilon_r' - i\epsilon_r''\right)$$

Wave equation becomes Helmholtz equation:

$$\frac{\partial^2 E_x}{\partial z^2} + k^2 E_x = 0, \quad k = \omega \sqrt{\mu \epsilon}$$

$$E_x = A e^{i(\omega t - kz)} + B e^{i(\omega t + kz)} = E_x^+ + E_x^-$$
$$ZH_y = A e^{i(\omega t - kz)} - B e^{i(\omega t + kz)} = ZH_y^+ - ZH_y^-$$


loss-free material: $k = \omega/c = 2\pi/\lambda$

lossy dielectric: $k = \omega \sqrt{\mu \epsilon_r \epsilon_0} = \beta - i\alpha$

α : *attenuation constant*, β : *phase constant*

$$\frac{\beta}{k_0} = \sqrt{\frac{\epsilon_r'}{2} + \frac{\epsilon_r'}{2} \sqrt{1 + \left(\frac{\epsilon_r''}{\epsilon_r'}\right)^2}}, \quad \frac{\alpha}{k_0} = \sqrt{-\frac{\epsilon_r'}{2} + \frac{\epsilon_r'}{2} \sqrt{1 + \left(\frac{\epsilon_r''}{\epsilon_r'}\right)^2}}$$

real physical field: $E_x^+ = \Re A e^{i(\omega t - kz)} = A \cos(\omega t - \beta z) e^{-\alpha z}$



Low-loss dielectrics: $\epsilon'' \ll \epsilon'$

$$\beta \approx \sqrt{\epsilon_r'} k_0, \quad \alpha \approx \frac{1}{2} \frac{\epsilon_r''}{\sqrt{\epsilon_r'}} k_0, \quad Z \approx \frac{Z_0}{\sqrt{\epsilon_r'}} \left(1 + \frac{i}{2} \frac{\epsilon_r''}{\epsilon_r'} \right)$$

Example: Polyamide (nylon)

$$\kappa = 10^{-8} \Omega^{-1} \text{m}^{-1}, \quad \epsilon_r = 3, \quad f = 10 \text{MHz}$$

11% attenuation in 100km, arc $Z \approx 10^{-4}^\circ$

Very good conductors (metallic): $\epsilon'' \approx -i\kappa/\omega \gg \epsilon'$

$$\beta \approx \alpha \approx \sqrt{\frac{\omega \mu \kappa}{2}} = \frac{1}{\delta_s}, \quad Z \approx (1+i) \frac{\alpha}{\kappa}, \quad \text{arc } Z = 45^\circ$$

Skin depth ($z = \delta_s$): $e^{-\alpha \delta_s} = \frac{1}{e} \rightarrow \alpha \delta_s = 1$

In general, β is a function of ω and is called dispersion relation. Developing β around ω_0

$$\beta(\omega) = \beta(\omega_0) + \left(\frac{d\beta}{d\omega} \right)_{\omega_0} d\omega + O[(d\omega)^2]$$

Phase velocity

$$\phi = \omega t \mp \beta z = \text{const.} \quad \rightarrow \quad \frac{d\phi}{dt} = \omega \mp \beta \frac{dz}{dt} = \omega \mp \beta v_{ph} = 0$$

$$v_{ph} = \pm \frac{\omega}{\beta(\omega_0)}$$

v_{ph} has no physical importance. Monochromatic waves carry no information.

Example: Water waves at shore

Group velocity (velocity with which a signal propagates)

As an example take two plane waves with ω_1 and ω_2

$$\omega_1 = \omega_0 + \delta \omega, \quad \omega_2 = \omega_0 - \delta \omega$$

$$\beta_1 = \beta_0 + \delta \beta, \quad \beta_2 = \beta_0 - \delta \beta$$

$$\Re [e^{i(\omega_1 t - \beta_1 z)} + e^{i(\omega_2 t - \beta_2 z)}] = 2 \cos(\delta \omega t - \delta \beta z) \cos(\omega_0 t - \beta_0 z)$$

$$v_g = \frac{\delta \omega}{\delta \beta} \rightarrow v_g = \left(\frac{d \omega}{d \beta} \right)_{\omega_0}$$


v_g is the velocity with which the envelope propagates.

Signals with **small** bandwidth $2\delta\omega$ propagate with v_g .

Large bandwidth signals require higher order terms $O((\delta\omega)^2)$.

Energy velocity

Energy transported
by Δz in time Δt :




$$\frac{\bar{w} \Delta A \Delta z}{\Delta t} = S_{cz} \Delta A \quad \rightarrow \quad v_e = \frac{\Delta z}{\Delta t} = \frac{S_{cz}}{\bar{w}}$$

for plane waves

$$S_{cz} = \frac{1}{2} (\vec{E} \times \vec{H}^*)_z = \frac{|E_0|^2}{2Z}, \quad \bar{w} = \frac{1}{4} \vec{E} \cdot \vec{D}^* + \frac{1}{4} \vec{H} \cdot \vec{B}^* = \frac{1}{2} \epsilon |E_0|^2$$

$$v_e = \frac{1}{Z\epsilon} = \frac{1}{\sqrt{\mu\epsilon}} = c$$

Cylindrical, ideal conducting waveguides



Substituting one of the 2 first Maxwell's equ. into the other gives a 2nd order diff. equ., which requires 2 independent functions. The 3^d and 4th equ. are additional conditions. These conditions and the required independent functions are fulfilled by

$$\vec{\nabla} \cdot \vec{E} = 0 \quad \rightarrow \quad \vec{E}^{TE} = \vec{\nabla} \times \vec{A}^{TE}, \quad \vec{A}^{TE} = A^{TE} \vec{e}_z, \quad TE\text{-waves}$$

$$\vec{\nabla} \cdot \vec{H} = 0 \quad \rightarrow \quad \vec{H}^{TM} = \vec{\nabla} \times \vec{A}^{TM}, \quad \vec{A}^{TM} = A^{TM} \vec{e}_z, \quad TM\text{-waves}$$

With the vector potentials A one gets e.g. for TE-waves

$$\vec{\nabla} \times \vec{H} = \epsilon \frac{\partial \vec{E}}{\partial t} = \epsilon \frac{\partial}{\partial t} \vec{\nabla} \times \vec{A} \quad \rightarrow \quad \vec{\nabla} \times \left(\vec{H} - \epsilon \frac{\partial \vec{A}}{\partial t} \right)$$

$$\rightarrow \quad \vec{H} = \vec{\nabla} \Phi + \epsilon \frac{\partial \vec{A}}{\partial t}$$

and from Maxwell's 2nd equ.

$$\vec{\nabla} \times \vec{E} = -\mu \frac{\partial \vec{H}}{\partial t} \quad \rightarrow$$

$$\vec{\nabla} \times (\vec{\nabla} \times \vec{A}) = \vec{\nabla} (\vec{\nabla} \cdot \vec{A}) - \vec{\nabla}^2 \vec{A} = -\vec{\nabla} \left(\mu \frac{\partial \Phi}{\partial t} \right) - \mu \epsilon \frac{\partial^2 \vec{A}}{\partial t^2}$$

\vec{A} , Φ are not fully determined. Substituting

$$\vec{A} \rightarrow \vec{A} + \vec{\nabla} \psi, \quad \Phi \rightarrow \Phi - \epsilon \partial \psi / \partial t$$

yields the same \vec{E} , \vec{H} .

One can make a gauge-transformation and choose e.g. the Lorenz gauge

$$\vec{\nabla} \cdot \vec{A} = -\mu \frac{\partial \Phi}{\partial t}$$

which results in a vectorial wave equ.


$$\vec{\nabla}^2 \vec{A} - \frac{1}{c^2} \frac{\partial^2 \vec{A}}{\partial t^2} = 0$$

Similarly, we proceed for the TM-case and obtain the same equ.. Since A has only a cartesian component, the vectorial wave equ. becomes a scalar one and in case of time-harmonic fields a scalar Helmholtz equ.

$$\vec{\nabla}^2 A^p + k^2 A^p = 0, \quad k = \frac{\omega}{c} = \omega \sqrt{\mu \epsilon}, \quad p = \left\{ \begin{array}{l} TE \\ TM \end{array} \right\}$$

Circular waveguide

Helmholtz equ. for circular cylinder coordinates:



$$\frac{1}{\rho} \frac{\partial}{\partial \rho} \left(\rho \frac{\partial A}{\partial \rho} \right) + \frac{1}{\rho^2} \frac{\partial^2 A}{\partial \varphi^2} + \frac{\partial^2 A}{\partial z^2} + k^2 A = 0 \quad (1)$$

Bernoulli ansatz: $A = R(\rho) \Phi(\varphi) Z(z)$

Substituted in (1) and division by $R\Phi Z$

$$\frac{1}{\rho R} \frac{\partial}{\partial \rho} \left(\rho \frac{\partial R}{\partial \rho} \right) + \frac{1}{\rho^2 \Phi} \frac{\partial^2 \Phi}{\partial \varphi^2} + \underbrace{\frac{1}{Z} \frac{\partial^2 Z}{\partial z^2}}_{-k_z^2} + k^2 = 0 \quad (2)$$

$$\frac{d^2 Z}{dz^2} + k_z^2 Z = 0 \rightarrow Z = C_1 e^{-ik_z z} + C_2 e^{ik_z z} \rightarrow C_1 e^{-ik_z z}$$

for waves propagating in +z-direction

(2) becomes with k_z

$$\frac{\rho}{R} \frac{\partial}{\partial \rho} \left(\rho \frac{\partial R}{\partial \rho} \right) + \underbrace{\frac{1}{\Phi} \frac{\partial^2 \Phi}{\partial \varphi^2}}_{-k_\mu^2} + \rho^2 (k^2 - k_z^2) = 0 \quad (3)$$

$$\begin{aligned} \frac{d^2 \Phi}{d\varphi^2} + k_\mu^2 \Phi = 0 &\rightarrow \Phi = C_3 \cos(k_\mu \varphi) + C_4 \sin(k_\mu \varphi) \\ &\rightarrow \Phi = C_3 \cos(m \varphi) \end{aligned}$$

because of 2π -periodicity and free choice of origin

With m and k_z (3) becomes Bessel's equ.

$$\frac{\partial^2 R}{\partial \rho^2} + \frac{1}{\rho} \frac{\partial R}{\partial \rho} + \left[k_c^2 - \frac{m^2}{\rho^2} \right] R = 0, \quad k_c = \sqrt{k^2 - k_z^2}$$

$$R = C_5 J_m(k_c \rho) + C_6 N_m(k_c \rho) \rightarrow R = C_5 J_m(k_c \rho)$$

because Neumann's function is infinite at $\rho=0$

Vector potential :

$$A = C_m \cos(m\varphi) J_m(k_c \rho) e^{-ik_z z}$$

TE – waves: $\vec{E} = \vec{\nabla} \times (A \vec{e}_z)$

$$E_\varphi = -\partial A / \partial \rho \sim J_m'(k_c \rho)$$

$$E_\varphi(\rho=a) = 0 \rightarrow k_{cmn} a = j'_{mn}$$

j'_{mn} : n^{th} non vanishing zero of J'_m

$$E_\rho = \frac{1}{\rho} \frac{\partial A}{\partial \phi} = -\frac{m}{\rho} C_{mn} \sin(m\varphi) J_m\left(j'_{mn} \frac{\rho}{a}\right) e^{-ik_z z}$$

$$E_\varphi = -\frac{\partial A}{\partial \rho} = -\frac{j'_{mn}}{a} C_{mn} \cos(m\varphi) J'_m\left(j'_{mn} \frac{\rho}{a}\right) e^{-ik_z z}$$

$$\vec{\nabla} \times \vec{E} = -i\omega\mu \vec{H}:$$

$$H_\rho = \frac{k_z}{\omega\mu} \frac{j'_{mn}}{a} C_{mn} \cos(m\varphi) J'_m\left(j'_{mn} \frac{\rho}{a}\right) e^{-ik_z z}$$

$$H_\varphi = -\frac{k_z}{\omega\mu} \frac{m}{\rho} C_{mn} \sin(m\varphi) J_m\left(j'_{mn} \frac{\rho}{a}\right) e^{-ik_z z}$$

$$H_z = \frac{-1}{i\omega\mu} \left(\frac{j'_{mn}}{a}\right)^2 C_{mn} \cos(m\varphi) J_m\left(j'_{mn} \frac{\rho}{a}\right) e^{-ik_z z}$$

$$TM - \text{waves: } \vec{H} = \vec{\nabla} \times (A \vec{e}_z), \quad \vec{\nabla} \times \vec{H} = i \omega \epsilon \vec{E}$$

$$E_z = \frac{k_c^2}{i \omega \epsilon} A \sim J_m(k_c \rho), \quad E_z(\rho = a) = 0 \rightarrow k_{cmn} a = j_{mn}$$

$$H_\rho = -\frac{m}{\rho} D_{mn} \sin(m \varphi) J_m\left(j_{mn} \frac{\rho}{a}\right) e^{-ik_z z}$$

$$H_\varphi = -\frac{j_{mn}}{a} D_{mn} \cos(m \varphi) J'_m\left(j_{mn} \frac{\rho}{a}\right) e^{-ik_z z}, \quad H_z = 0$$

$$E_\rho = -\frac{k_z}{\omega \epsilon} \frac{j_{mn}}{a} D_{mn} \cos(m \varphi) J'_m\left(j_{mn} \frac{\rho}{a}\right) e^{-ik_z z}$$

$$E_\varphi = \frac{k_z}{\omega \epsilon} \frac{m}{\rho} D_{mn} \sin(m \varphi) J_m\left(j_{mn} \frac{\rho}{a}\right) e^{-ik_z z}$$

$$E_z = \frac{1}{i \omega \epsilon} \left(\frac{j_{mn}}{a}\right)^2 D_{mn} \cos(m \varphi) J_m\left(j_{mn} \frac{\rho}{a}\right) e^{-ik_z z}$$

The ratio of the transverse field components is the field (wave) impedance

$$Z_F = \frac{E_\rho}{H_\varphi} = -\frac{E_\varphi}{H_\rho} = \left\{ \begin{array}{l} Z_F^{TE} = \frac{\omega \mu}{k_z} \\ Z_F^{TM} = \frac{k_z}{\omega \epsilon} \end{array} \right.$$

The dependence of the propagation constant k_z on frequency is the dispersion relation

$$k_{cmn}^2 = k^2 - k_{zmn}^2 \rightarrow k_{zmn} = \sqrt{k^2 - k_{cmn}^2}$$

$$k_{zmn} = \left\{ \begin{array}{ll} \text{real} & k > k_{cmn} \quad \textit{propagation} \\ 0 & \textit{for } k = k_{cmn} \\ \text{imaginary} & k < k_{cmn} \quad \textit{attenuation} \end{array} \right.$$

critical wavenumber : $k_{cmn} = \begin{cases} j_{mn}'/a & \text{for } TE \\ j_{mn}/a & \text{for } TM \end{cases}$

cutoff frequency : $f_{cmn} = c k_{cmn} / 2\pi$

cutoff wavelength : $\lambda_{cmn} = 2\pi / k_{cmn}$

guide wavelength : $\lambda_{zmn} = 2\pi / k_{zmn} = \frac{\lambda}{\sqrt{1 - (\lambda/\lambda_{cmn})^2}}$

free space wavelength λ

energy flux density $S_{cz} = \frac{1}{2} (\vec{E} \times \vec{H}^*)_z = \frac{1}{2} Z_F [|H_\rho|^2 + |H_\phi|^2]$


$$= \begin{cases} \text{imaginary} & \text{for } k < k_c \\ 0 & \text{for } k = k_c \\ \text{real} & \text{for } k > k_c \end{cases}$$

Each mn defines a certain (eigen-) mode. The general solution is the linear combination of all modes


$$\vec{E} = \sum_m \sum_n (\vec{E}_{mn}^{TE} + \vec{E}_{mn}^{TM}), \quad \vec{H} = \sum_m \sum_n (\vec{H}_{mn}^{TE} + \vec{H}_{mn}^{TM})$$

Modes are normally sorted referring to their cutoff frequency:

type	m	n	(f_c / GHz)(a/cm)
TE	1	1	8.78
TM	0	1	11.46
TE	2	1	14.56
TE/TM	0/1	1/1	18.29
TE	3	1	20.05




Copper waveguide with $a=2.5$ cm



Impedance boundary condition on good conductors $(|\delta D/\delta t| \ll |J|)$

Fields on metallic surfaces:
 $E \approx \text{perp}$, $H \approx \text{parallel}$



We decompose the fields and the nabla operator into tangential and normal components

$$\vec{E} = \vec{E}_t + E_z \vec{e}_z, \quad \vec{H} = \vec{H}_t + H_z \vec{e}_z, \quad \vec{\nabla} = \vec{\nabla}_t + \vec{e}_z \frac{\partial}{\partial z}$$

and subsequently also Maxwell's eqs.:

$$\vec{\nabla} \times \vec{H} = \kappa \vec{E}: \quad \vec{E}_t = -\frac{1}{\kappa} \vec{e}_z \times \vec{\nabla}_t H_z + \frac{1}{\kappa} \vec{e}_z \times \frac{\partial \vec{H}_t}{\partial z}$$

$$E_z \vec{e}_z = \frac{1}{\kappa} \vec{\nabla}_t \times \vec{H}_t$$

$$\vec{\nabla} \times \vec{E} = -i \omega \mu_0 \vec{H}: \quad \vec{H}_t = -\frac{i}{\omega \mu_0} \vec{e}_z \times \vec{\nabla}_t E_z + \frac{i}{\omega \mu_0} \vec{e}_z \times \frac{\partial \vec{E}_t}{\partial z}$$

$$H_z \vec{e}_z = \frac{i}{\omega \mu_0} \vec{\nabla}_t \times \vec{E}_t$$

Tangential to the surface the typical length of change is λ_0 .
 Normal to the surface, in metal, the typical length of change is $\delta_s \ll \lambda_0$.

With an order of magnitude approximation $|\vec{\nabla}_t| \sim 1/\lambda_0$ one gets for the magnitude of E_z and H_z

$$|E_z| = \left| \frac{1}{\kappa} \vec{\nabla}_t \times \vec{H}_t \right| \sim \frac{1}{\kappa \lambda_0} |\vec{H}_t| = \pi \left(\frac{\delta_s}{\lambda_0} \right)^2 Z_0 |\vec{H}_t|$$

$$Z_0 |H_z| = \left| \frac{i}{\omega \mu_0} \vec{\nabla}_t \times \vec{E}_t \right| \sim \frac{1}{\omega \mu_0} \frac{Z_0}{\lambda_0} |\vec{E}_t| = \frac{1}{2\pi} |\vec{E}_t|.$$

With that we estimate the green terms

$$\left| \frac{1}{\kappa} \vec{e}_z \times \vec{\nabla}_t H_z \right| \sim \frac{1}{\kappa \lambda_0} |H_z| = \pi \left(\frac{\delta_s}{\lambda_0} \right)^2 Z_0 |H_z| \sim \frac{1}{2} \left(\frac{\delta_s}{\lambda_0} \right)^2 |\vec{E}_t|$$

$$\left| \frac{i}{\omega \mu_0} \vec{e}_z \times \vec{\nabla}_t E_z \right| \sim \frac{1}{\omega \mu_0 \lambda_0} |E_z| = \frac{1}{2\pi Z_0} |E_z| \sim \frac{1}{2} \left(\frac{\delta_s}{\lambda_0} \right)^2 |\vec{H}_t|.$$

One finds that they can be neglected compared to E_t , H_t .

So, the tangential parts of Maxwell's equs. are simplified to

$$\kappa \vec{E}_t \approx \vec{e}_z \times \frac{\partial \vec{H}_t}{\partial z} \quad (1)$$

$$i \omega \mu_0 \vec{H}_t \approx -\vec{e}_z \times \frac{\partial \vec{E}_t}{\partial z}.$$

Eliminating \vec{E}_t one gets an equ. for \vec{H}_t

$$\frac{\partial^2 \vec{H}_t}{\partial z^2} - i \omega \mu_0 \kappa \vec{H}_t = 0$$

with the solution


$$\vec{H}_t = \vec{H}_{t0} e^{-(1+i)z/\delta_s}. \quad (2)$$

(2) substituted into (1) gives a boundary condition at real (non – ideal) metallic surfaces

$$\vec{E}_{t0} \approx Z_W (\vec{n} \times \vec{H}_{t0}), \quad Z_W = \frac{1+i}{\kappa \delta_s}.$$

Attenuation in waveguides

(power-loss method)



conservation of power : $\frac{dP(z)}{dz} = -P_d'$

$\vec{E}, \vec{H} \sim e^{-\alpha z}, P(z) \sim e^{-2\alpha z} \rightarrow \frac{dP(z)}{dz} = -2\alpha P(z) = -P_d'$

dissipation per waveguide surface area:

$$\frac{\Delta P_d}{\Delta A} = -\vec{n} \cdot \Re(\vec{S}_c) = -\frac{1}{2} \Re(\vec{n} \cdot (\vec{E}_{t0} \times \vec{H}_{t0}^*)) = \frac{1}{2} \Re(Z_w) |\vec{H}_{t0}|^2$$

$$\frac{\Delta P_d}{\Delta A} = \frac{1}{2 \kappa \delta_s} |\vec{H}_{t0}|^2$$

dissipation per waveguide length:

$$P_d' = \frac{1}{2 \kappa \delta_s} \oint |\vec{H}_{t0}|^2 ds$$

transported active power:

$$\begin{aligned} P(z) &= \iint \Re(\vec{S}_c) \cdot d\vec{A} = \frac{1}{2} \iint \Re(\vec{E} \times \vec{H}^*) \cdot \vec{e}_z dA = \\ &= \frac{1}{2} \iint \Re(\vec{E}_{transv} \times \vec{H}_{transv}^*)_z dA = \frac{1}{2} Z_F \iint |H_{transv}|^2 dA \end{aligned}$$

attenuation:
$$\alpha = \frac{1}{2} \frac{P_d'}{P(z)}$$

Resonant cavities

Example: Cylindrical cavity, radius a , length g , TM-modes

Forward plus backward traveling wave from transparency 49

$$E_{\varphi} = \frac{k_z}{\omega \epsilon} \frac{m}{\rho} D_{mn} \sin(m\varphi) J_m(k_{cmn}\rho) [e^{-ik_z z} - r_{mn} e^{ik_z z}]$$

Boundary conditions

$$E_{\varphi}(z=0) = 0 \quad \rightarrow \quad r_{mn} = 1, \quad E_{\varphi} \sim \sin(k_z z)$$

$$E_{\varphi}(z=g) = 0 \quad \rightarrow \quad k_{zp} g = p\pi, \quad p = 0, 1, 2, \dots$$

Vector potential

$$A = 2D \cos(m\varphi) \cos(k_{zp} z) J_m(k_{cmn}\rho)$$

Fields:

$$H_{\rho} = -2 \frac{m}{\rho} D_{mnp} \sin(m\varphi) \cos(k_{zp} z) J_m(k_{cmn} \rho)$$

$$H_{\varphi} = -2 k_{cmn} D_{mnp} \cos(m\varphi) \cos(k_{zp} z) J_m'(k_{cmn} \rho), \quad H_z = 0$$

$$E_{\rho} = i 2 \frac{k_{zp}}{\omega \epsilon} k_{cmn} D_{mnp} \cos(m\varphi) \sin(k_{zp} z) J_m'(k_{cmn} \rho)$$

$$E_{\varphi} = -i 2 \frac{k_{zp}}{\omega \epsilon} \frac{m}{\rho} D_{mnp} \sin(m\varphi) \sin(k_{zp} z) J_m(k_{cmn} \rho)$$

$$E_z = -i 2 \frac{k_{cmn}^2}{\omega \epsilon} D_{mnp} \cos(m\varphi) \cos(k_{zp} z) J_m(k_{cmn} \rho)$$

$$k_{cmn} = \sqrt{k^2 - k_{zp}^2} = \frac{j_{mn}}{a} \quad \rightarrow \quad k_{mnp} = \frac{\omega_{mnp}}{c_0} = \left(\frac{j_{mn}}{a} \right)^2 + k_{zp}^2$$

Example: TM_{010} -resonator ($m=0, n=1, p=0$)

$$H_{\varphi} = 2 \frac{j_{01}}{a} D_{010} J_1 \left(j_{01} \frac{\rho}{a} \right)$$

$$E_z = -i \frac{2}{\omega \epsilon} \left(\frac{j_{01}}{a} \right)^2 D_{010} J_0 \left(j_{01} \frac{\rho}{a} \right)$$

Resonance frequency

$$k_{010} = \frac{\omega_{010}}{c_0} = k_{c01} = \frac{j_{01}}{a}$$

$$f_{010} = \frac{\omega_{010}}{2\pi} = \frac{j_{01} c_0}{2\pi a}$$

Stored energy

$$\bar{W} = \bar{W}_e + \bar{W}_m = 2 \bar{W}_e = \frac{1}{2} \iiint \vec{E} \cdot \vec{D}^* dV = \frac{\epsilon}{2} \iiint |E_z|^2 dV$$

$$\bar{W} = \frac{2\pi g}{\omega_{010}^2 \epsilon a^2} |D_{010}|^2 J_1^2(j_{01})$$

Dissipation per unit area

$$\bar{P}_d'' = \frac{1}{2\kappa\delta_s} |\vec{H}_{t0}|^2$$

total dissipation

$$\bar{P}_d = \iint \bar{P}_d'' dA = \frac{4\pi}{\kappa\delta_s} j_{01}^2 \left(1 + \frac{g}{a}\right) |D_{010}|^2 J_1^2(j_{01})$$

Quality factor (Q-value)

$$Q_0 = \frac{\omega_{010} \bar{W}}{\bar{P}_d} = \frac{1}{\delta_s} \frac{g}{1 + g/a} \rightarrow \delta_s Q_0 = 2 \frac{V}{S} \sim \frac{\text{Volume}}{\text{Surface}}$$

Q_0 gives the decay rate of the stored energy or the time T_f to fill the cavity.

From *power conservation*

$$-\frac{d\bar{W}}{dt} = \bar{P}_d = \frac{\omega_{010}}{Q_0} \bar{W} \quad \rightarrow \quad \bar{W} = \bar{W}_0 e^{-2t/T_f}, \quad T_f = 2 \frac{Q_0}{\omega_{010}}$$

Example: 3 GHz copper cavity, $g = \lambda_{010}/2 = 5$ cm

$$j_{01} = 2.405, \quad J_1(j_{01}) = 0.5191, \quad \kappa = 58 \cdot 10^6 \Omega^{-1} \text{m}^{-1}$$

$$a = 3.83 \text{ cm}, \quad \delta_s = 1.21 \mu\text{m}, \quad Q_0 = 17963, \quad T_f = 1.9 \mu\text{s}$$

Resonance behaviour of a cavity mode

Instead of lossy walls assume ideal conducting walls and lossy dielectric filling. That preserves the ideal mode but allows for studying losses.

The cavity is driven by a current \vec{J} passing through it. \vec{J} splits into a conduction current $\vec{J}_c = \kappa \vec{E}$, responsible for the losses in the dielectric, and in an enforced current \vec{J}_0 as driving term:

$$\begin{aligned}\vec{\nabla} \times (\vec{\nabla} \times \vec{E}) &= \vec{\nabla} (\vec{\nabla} \cdot \vec{E}) - \vec{\nabla}^2 \vec{E} = -\mu \frac{\partial}{\partial t} \vec{\nabla} \times \vec{H} = \\ &= -\mu \frac{\partial}{\partial t} (\vec{J}_0 + \kappa \vec{E} + \epsilon \frac{\partial \vec{E}}{\partial t}) \\ \vec{\nabla}^2 \vec{E} - \mu \kappa \frac{\partial \vec{E}}{\partial t} - \mu \epsilon \frac{\partial^2 \vec{E}}{\partial t^2} &= \mu \frac{\partial \vec{J}_0}{\partial t} \quad \text{with gauge} \quad \vec{\nabla} \cdot \vec{E} = 0\end{aligned}$$

We expand \vec{E} in (eigen-)modes

$$\vec{E} = \sum_r a_r(t) \vec{e}_r(x, y, z), \quad r \text{ goes over all } m, n, p \quad (2)$$

where $\vec{\nabla}^2 \vec{e}_r + k_r^2 \vec{e}_r = 0$

$$\vec{\nabla} \cdot \vec{e}_r = 0 \text{ in volume,} \quad \vec{n} \times \vec{e}_r = 0 \text{ on walls}$$

$$\iiint \vec{e}_r \cdot \vec{e}_s dV = \delta_r^s$$

Substituting (2) in (1) and deviding by $-\mu\epsilon$

$$\sum_r \left[\frac{d^2 a_r}{dt^2} + \frac{\kappa}{\epsilon} \frac{da_r}{dt} + \frac{k_r^2}{\mu\epsilon} a_r \right] \vec{e}_r = -\frac{1}{\epsilon} \frac{\partial \vec{J}_0}{\partial t}. \quad (3)$$

Multiplying (3) with e_s and integrating over V



$$\frac{d^2 a_s}{dt^2} + \frac{\kappa}{\epsilon} \frac{da_s}{dt} + \frac{k_s^2}{\mu \epsilon} a_s = -\frac{1}{\epsilon} \iiint \frac{\partial \vec{J}_0}{\partial t} \cdot \vec{e}_s dV = \frac{\partial f_s}{\partial t}. \quad (4)$$

In case of time-harmonic excitation (4) becomes


$$\left[-\omega^2 + i \frac{\kappa}{\epsilon} \omega + \frac{k_s^2}{\mu \epsilon} \right] a_s = i \omega f_s$$

$$a_s = \frac{Q_s}{\omega_s} \frac{f_s}{1 + i Q_s \left[\frac{\omega}{\omega_s} - \frac{\omega_s}{\omega} \right]}, \quad \omega_s = c k_s, \quad Q_s = \frac{\epsilon \omega_s}{\kappa}.$$

Now replace Q_s by Q_0 as calculated with impedance-boundary-condition and ω_s by the resonance frequency ω_{mnp} .



Well separated modes can be represented by a lumped element resonator



$$\omega_s = \frac{1}{\sqrt{L_s C_s}}, \quad Q_s = \frac{\omega_s W_s}{P_{ds}} = \omega_s R_s C_s$$

Bandwidth

$$B_s = \frac{(\omega_s + \delta\omega) - (\omega_s - \delta\omega)}{\omega_s} = 2 \frac{\delta\omega}{\omega_s} = \frac{1}{Q_s}$$

Filling time

$$T_{fs} = 2 \frac{Q_s}{\omega_s} = \frac{1}{\delta\omega}$$

Accelerating voltage for a particle passing the cavity on-axis with velocity v

$$V_s = \left| \int_0^g a_s \vec{e}_s \cdot \vec{e}_z e^{i\omega t} dz \right|, \quad z = vt$$

Shunt impedance (available V_s for given P_{ds})

$$R_{shs} = \frac{V_s^2}{P_{ds}} = 2R_s$$

R-upon-Q (available V_s for given W_s , geometrical quantity, independent of losses)

$$\frac{R_{shs}}{Q_s} = \frac{V_s^2}{\omega_s W_s} = \frac{2}{\omega_s C_s}$$

ω_s , Q_s and R_{shs}/Q_s define R_s , L_s , C_s .

Literature:

David K. Cheng, Field and wave electromagnetics.
Addison-Wesley 1990


David J. Griffiths, Introduction to electrodynamics.
Prentice Hall 1999

J. D. Jackson, Classical electrodynamics.
John Wiley & Sons 1975

Exercise 1:


Given is a conducting hollow sphere carrying a charge Q . What is the field inside and outside and what is the stored energy?

If the sphere is a model for an electron ($E_{0e} = 511\text{keV}$) what is then the classical electron radius $r_e = a$?




Exercise 2:

A capacitor is filled with a lossy dielectric and charged to a voltage V . What is the time constant for discharge?



Exercise 3:

A long dipole magnet is excited by a coil with n windings and current I_0 . Calculate the magnetic field in the air gap.



Exercise 4:

Derive the multi-poles for a static 2-dimensional magnetic field. Remark: Solve the magnetic potential equation in circular cylindrical coordinates and free-space.


Exercise 5:

Give the E- and H-field of a z-polarized plane wave which propagates in x-direction.
What is the time-averaged radiated power density?

Exercise 6:

Derive the longitudinal vector potential for TM-waves in a rectangular waveguide.

What is the equation for the separation constants?



Exercise 7:

Give the guide wavelength and phase and group velocity of a TM_{11} -mode in a rectangular waveguide.

Exercise 8:

Calculate the accelerating voltage, shunt impedance and R-upon-Q of a TM_{110} -mode in a rectangular cavity resonator with dimensions a, b, g .